



Windows Local Kernel Exploitation

sk@scan-associates.net




- Windows Privilege Escalations
- Windows Kernel 101
- Device driver communication problem
 - DeviceIOControl
 - Finding
 - Exploiting
- Kernel shellcode
- Locating base address of device
 - Undocumented API (NtQuerySystemInformation)
- Demo

- Exploiting SYSTEM privilege application:
 - Buffer overflow in Still Image Service
 - IIS IDQ.DLL
 - Buffer overflow in POSIX subsystem
- LPC problems
- Named pipe impersonation
- Shatter attack
- Kernel bugs

- Local Procedure Call allows processes to communicate
- Various problems discovered by Todd Sabin
- NtImpersonateClientOfPort()
 - http://www.bindview.com/Support/RAZOR/Advisories/2000/adv_NTPromotion.cfm
 - <http://www.bindview.com/Support/RAZOR/Advisories/2000/LPCAdvisory.cfm>
- Signedness problem in NTLM Security Support Provider (NTLMSSP) LPC port
 - http://www.bindview.com/Support/RAZOR/Advisories/2001/adv_NTLMSSP.cfm



- A server named pipe can impersonate its client
- Attacker create named pipe before the server create it
- A privileged client connect to our server named pipe, we can impersonate the client to get its privilege
- <http://www.blakewatts.com/namedpipepaper.html>




- IIS always load certain file with specific filename using SYSTEM privilege
- By creating filename such as:
 - IDQ.DLL
 - httpext.dll
 - httpodbc.dll, etc


• <http://www.xfocus.org/exploits/200110/7.html>

- Send Windows Message to any process
- Basic Shatter:
 - Locate a privileged Windows
 - Send shellcode to target process space
 - Send WM_TIMER message to jump to shellcode in its own space
- Advance Shatter is still just Shatter
- Require Desktop
- Also known as *Local/Local* attack
- Limited use

- Problems that exist in Kernel land
- Will give us highest access, same level as the OS
- Windows Kernel is not a well documented
- Generally more complex than user land
- Probably still plenty of 'fish'
- Kernel bugs is gaining popular J



- Buffer Overrun in Windows Kernel Message Handling
 - <http://www.microsoft.com/technet/security/bulletin/MS03-013.msp>
- Windows VDM TIB
 - <http://www.eeye.com/html/research/advisories/AD20040413E.html>
- Windows Expand-Down Data Segment
 - <http://www.eeye.com/html/research/advisories/AD20040413D.html>
- Device Driver Communication Problem
 - <http://sec-labs.hack.pl/papers/win32ddc.php>





User Land	Kernel Land
Ring 3	Ring 0
Each process has 2GB memory	Every kernel modules, device driver share the same 2GB memory
Memory address from 0x00000000 to 0x7FFFFFFF	Memory address from 0x80000000 to 0xFFFFFFFF
Sandbox!	Freedom!

- Windows kernel land consists of:
 - Kernel
 - Executives
 - Process and Thread manager, I/O Manager, etc
 - Win32 User GDI
 - Device Driver
- The kernel contains many important executives object which control the application in user land

- Loadable Kernel Module (LKM)
- Once in kernel, Device Driver is trusted
- Ability to modify kernel object to change behavior of application in user land
- Application such as Personal firewall, Antivirus, etc sometimes install Device Driver to change behavior of user land:
 - Check all socket connections
 - Check all file access, etc

- Device driver can accept data from user land via:
 - ReadFile / WriteFile()
 - DeviceIoControl()
- Before it can be used, we must open the driver:
 - CreateFile()
- We can access device driver much like a file





- Basic device driver
 - **DriverEntry()**
 - **DriverDispatcher()**
 - **DriverUnload()**
- Data from **DeviceIoControl()** will be process in **DriverDispatcher()**




17.3.1976
Alla mia amata
Anastasia perché
si ricorda qualche
volta di me. Ah
ciao aff.
Umberto Bonivento

Stimabilissima
Contessa Bontà
voglio augurarvi




- Communication between user land and kernel land
- User program send control code to device driver via **DeviceloControl()** API
- Device driver receive control code and process
- Device driver return output to user land via output pointer specified by caller




- **BOOL DeviceIoControl**(
 HANDLE *hDevice*, // handle to device
 DWORD *dwIoControlCode*, // operation
 LPVOID *lpInBuffer*, // input data buffer
 DWORD *nInBufferSize*, // size of input data
 //buffer
 LPVOID *lpOutBuffer*, // output data buffer **DWORD**
 nOutBufferSize, // size of output
 //data buffer
 LPDWORD *lpBytesReturned*, // byte count **LPOVERLAPPED**
 lpOverlapped //overlapped
 //information
);

- What if output buffer is a memory address in kernel?
- Will we be able to overwrite any kernel address?
- What if we point it to overwrite important token?
- What if we overwrite function pointer?
- (Un)Fortunately, I/O Manager provides buffer handling for device driver



- Buffered I/O (Method 0)
 - I/O manager allocates enough buffer copy from/to sender's data
- Direct I/O (Method 1 and 2)
 - Sender's buffer is lock and I/O manager pass the pointer of the memory to driver
- Neither I/O (Method 3)
 - No buffer management

- `#define CTL_CODE(DeviceType, Function, Method, Access)`
`((DeviceType) << 16) | ((Access) << 14) | ((Function) << 2) |`
`(Method);`



- Device I/O Control Code that ends with 011b
 - 0XXXXXXXX3
 - 0XXXXXXXX7
 - 0XXXXXXXXB
 - 0XXXXXXXXF
- Output pointer can be anywhere, including kernel land
- Arbitrary memory write

- Source code and Header file
- Application hooking
 - **strace -p PID**
- Hook system wide ***DeviceloControl***
 - From the book, “Undocumented Windows 2000 Secrets”
 - **C:\w2k_hook *DeviceloControl***

- Bug found by mslug
(<https://www.xfocus.net/bbs/index.php?act=SE&f=16&t=32580&p=115340&hl=>)
 - #define BIOCGSTATS 9031 //0x2347
- Other potential targets in Packet.h:
 - #define BIOCISDUMPENDED 7411 //0x1CF3
 - #define BIOCSTRIMEOUT 7416 //0x1CF8
 - #define BIOCSDMODE 7412 //0x1CF4
 - #define BIOCSTRITEREP 7413 //0x1CF5
 - #define BIOCSDMINTOCOPY 7414 //0x1CF6
 - #define BIOCSDGEVNAME 7415 //0x1CF7
 - #define BIOCSDENDPACKETSSYNC 9033 //0x2349
 - #define BIOCSDSETDUMPLIMITS 9034 //0x234A

- C:\w2k_hook *DeviceIoControl*
 - 1CF:s0=NtDeviceIoControlFile(!2B8.3B4="\??\NAVAP",p,p,p,i0.4,n222A87,p3CFFEF8,n20,p3CFFEF0,n4)1C4963F2B6F71D0,530,3
 - 18D:s0=NtDeviceIoControlFile(!5C8.344="\Device\Tcp",p330,p,p,i0.38,n120003,p6F4D8,n24,pB01E90,n8000)1C494FBFF5C1960,42C,A
 - 606:s0=NtDeviceIoControlFile(!E4.898="\Device\Afd\Endpoint",p1E4,p,p,i0.0,n12047,p1A2F6F0,nD4,p,n0)1C495035A74B1E0,648,1D
 - 1:s0=NtDeviceIoControlFile(!354.120="\??\shadow",p,p,p,i0.0,n140FFB,p6B2F8,n0,n0)1C495C2244759C0,634,27
 - 3201:s0=NtDeviceIoControlFile(!1F0.2D8="\Device\LanmanDatagramReceiver",p2D0,p,p,i0.50,n130023,pD5FD24,n50,pA4FF8,n1000)1C4964E8570CB16,584,47

- Norton A/V Enterprise
- Contains NAVAP.sys device driver
- Allows communication from user program via **DeviceloControl()**
- The following CTL_CODE supported:
 - PAGE:0001649D cmp ecx, 222A83h
 - PAGE:000164A5 cmp ecx, 222A87h
 - PAGE:000164AD cmp ecx, 222A8Bh
 - PAGE:000164B5 cmp ecx, 222A8Fh
 - PAGE:000164BD cmp ecx, 222A93h
 - PAGE:000164C5 cmp ecx, 222A97h
 - PAGE:000164CD cmp ecx, 222A9Bh
- Uses **Neither I/O** heavily (for performance?)

- With the ability to write to kernel we can:
 - Overwrite return address
 - Overwrite function pointer
 - Overwrite switch jump table
 - Overwrite Service Descriptor Table
 - etc
- Once overwritten, kernel will jump to us when it reach that code

- Determine output value of the vulnerable **DeviceloControl()**
- Allocate memory which Device will jump to
 - **hMem = VirtualAlloc(myAddress, 0xf000, MEM_COMMIT, PAGE_EXECUTE_READWRITE);**
- Copy the shellcode into allocated memory
- Open the driver
 - **handler = CreateFile()**
- Send first signal to overwrite jump table
 - **DeviceloControl(handler, 0xFFFFFFFF7, inBuffer, 0x20, outBuffer, 4, &n, 0)**
- Send second signal to jump to shellcode

- Overwrite switch jump table
- Many Device Driver has switch statement to process user request in **DriverDispatcher()** that look like this:

```
NTSTATUS NPF_IoControl(IN PDEVICE_OBJECT DeviceObject,IN PIRP Irp)
```

```
{...
```

```
switch (FunctionCode){
```

```
    case BIOCGSTATS: //function to get the capture stats
```

```
        ...
```

```
        EXIT_SUCCESS(26);
```

```
        break;
```

```
    case BIOCGEVNAME:
```

```
        ...
```

```
        break;
```

```
    case BIOSENDPACKETSSYNC:
```

```
        ...
```

```
}
```

- In Assembly:


```
PAGE:0002F049 loc_2F049:                ; CODE XREF: sub_2F038+D j
PAGE:0002F049      mov     eax, [ebp+arg_0]
PAGE:0002F04C      dec     eax
PAGE:0002F04D      cmp     eax, 0Fh      ; switch 16 cases
PAGE:0002F050      ja     loc_2F3E1      ; default
PAGE:0002F056      jmp     ds:off_2F3E8[eax*4] ; switch jump
...
PAGE:0002F3E8 off_2F3E8      dd offset loc_2F05D    ; DATA XREF: sub_2F038+1E r
PAGE:0002F3E8      dd offset loc_2F08C    ; jump table for switch statement
PAGE:0002F3E8      dd offset loc_2F0AF
PAGE:0002F3E8      dd offset loc_2F0B9
PAGE:0002F3E8      dd offset loc_2F0C3
PAGE:0002F3E8      dd offset loc_2F0F4
PAGE:0002F3E8      dd offset loc_2F125
PAGE:0002F3E8      dd offset loc_2F154
```

- We can overwrite the first switch case at 0x2F3E8 with address of our shellcode
- Then, we call the **DeviceloControl()** again
- When it reach the first switch case again, it will jump to our shellcode
- However, the output from **DeviceloControl()** is always fixed at 0x4

- Address always overwritten with 0x4
- If we overwrite case 0 with 0x4, the next call to it will jump to 0x00000004
- We cant allocate memory at 0x00000004
- So, we overwrite the first two bytes of the second case

Overwrite here at 2F3EE

2F3E8




Case 0

Case 1

- Now, if we trigger Case 1, it will jump to:
 - 0x0004XXXX
- We can allocate memory 0x00040000 before calling Case 1

Overwrite here at 2F3EE


2F3E8




Case 0

Case 1

- Device driver will jump in to 0x0004XXXX after the second signal
- We need to allocate specific memory region:
 - `VirtualAlloc(0x00040000, 0xf000, MEM_COMMIT, PAGE_EXECUTE_READWRITE);`
- Copy our shellcode into the region



- What do we need to execute?
- Written by Eyas
- <http://www.xfocus.net/articles/200306/545.html>
- Technique:
 - Find System's token
 - Replace process's token pointer with System's token



- Locate the ETHREAD
 - fs:[0x124] or 0xffdff124
- From ETHREAD, we jump to EPROCESS
- Within EPROCESS, use **ActiveProcessLinks** to loop into all active process
- For each process, check the UniqueProcessId
- **SYSTEM** Pid is:
 - Win2k = 8
 - WinXP = 4
- Can use similar technique to find other PID

FS:0x124

0x00

_ETHREAD

_KTHREAD

_KAPC_STATE

***_EPROCESS**

0x44

...

_EPROCESS

***UniqueProcessId**

struct _LIST_ENTRY
ActiveProcessLinks


***Flink**

***Blink...**


...


***Token**

...



- Windows's Security Reference Monitor (SRM) uses token to identify process or thread
- To become SYSTEM, we just need a SYSTEM token
- A pointer to SYSTEM token is inside its EPROCESS
- Once we located SYSTEM process, we change our process token to point to SYSTEM token






Guest process


System Tokens

Guest Tokens




System process


- Need to overwrite the exact location of switch table
- Device driver base memory change every boot
- Use **NtQuerySystemInformation()**
- Get **SystemModuleInformation** list
- Compare Module name to get based address of any device driver




- Using **NtQuerySystemInformation()** again but getting processes list
SystemProcessesAndThreadsInformation
- Compare **ProcessName** to get **ProcessId**
- For each **ProcessId**, escalate it to SYSTEM



- The complete exploit is available from:
 - www.scan-associates.net/papers/navx.c



- Server allows us to upload *.*
- But every time we uploaded cmd.asp, it disappear
- Apparently, Norton A/V detects cmd.asp as trojan and delete it



- Encode cmd.asp using Microsoft Script Encoder
 - <http://www.microsoft.com/downloads/details.aspx?FamilyId=E7877F67-C447-4873-B1B0-21F0626A6329&displaylang=en>
- Upload cmdx.asp to get arbitrary command execution
- But we only get IUSR user **L**

- Upload navx.exe
- Run navx.exe
- Exploit escalate all DLLHOST into SYSTEM
- Command in cmdx.asp is now running as SYSTEM

